

# IT 认证电子书



质 量 更 高 服 务 更 好

半年免费升级服务

<http://www.itrenzheng.com>

**Exam : ACE-A1.2**

**Title : Arista Certified Engineering  
Associate Exam**

**Version : DEMO**

1. On EOS 4.13.1F, which of the following statements are true in regards to Arista's Tap Aggregation feature? (Select two)

- A. Tap ports are send only.
- B. Tap ports are receive only.
- C. Tool ports are send only.
- D. Tool ports are receive only.

**Answer:** AD

**Explanation:**

Reference:

[https://eos.arista.com/danz-tap-aggregation-configuration-getting-started/#Ports\\_and\\_Groups](https://eos.arista.com/danz-tap-aggregation-configuration-getting-started/#Ports_and_Groups)

2. Where does Aboot look for the boot system image at boot time?

- A. At the location specified in the running-config
- B. At the location specified in the startup-config
- C. At the location specified in a file named boot-config on flash:
- D. At the location specified in a file named boot\_config on flash:

**Answer:** C

**Explanation:**

Reference: <https://www.safaribooksonline.com/library/view/arista-warrior/9781449358921/ch18.html>

3. When ZTP is in enable mode, what triggers ZTP when the switch boots?

- A. A missing or zero-byte SWI image.
- B. A missing or zero-clue administrator.
- C. A missing or zero-byte startup-config file
- D. A missing or zero-byte running-config file

**Answer:** C

**Explanation:**

Reference: [https://eos.arista.com/ztp-set-up-guide/#ZTP\\_Boot](https://eos.arista.com/ztp-set-up-guide/#ZTP_Boot)

4. Which of the following are valid Event Manager triggers?

- A. on-boot
- B. on-schedule
- C. on-startup-config
- D. on-reload

**Answer:** AC

**Explanation:**

Reference: [https://eos.arista.com/introduction-to-managing-eos-devices-automation-and-extensibility/#521\\_Event\\_Manager](https://eos.arista.com/introduction-to-managing-eos-devices-automation-and-extensibility/#521_Event_Manager)

5. Which of the following Arista switch series' supports Zero Touch Provisioning (ZTP)?

- A. 7050
- B. 7280E
- C. 7300
- D. 7500E

**Answer:** D

**Explanation:**

Reference: <https://eos.arista.com/ztp-set-up-guide/> (see introduction)